SatPy - Part 1: Exploring Advanced Himawari Imager (AHI) data

For detailed documentation, visit SatPy Documentation.

SatPy is a powerful library for **reading**, **manipulating**, and **displaying** data from remote sensors, primarily related to meteorology. It also provides the capability to **save** this data as images or in various formats.

SatPy excels at generating images with **individual channels or bands** and creating **RGB composites** directly from satellite instrument data.

The pyresample library is used for **resampling data** in different areas with specific projections or uniform grids.

Additionally, Satpy offers various **atmospheric corrections** and **visual enhancements**, either directly within Satpy or through the PySpectral and TrollImage packages.

Advanced Himawari Imager (AHI) data

https://www.earthdata.nasa.gov/sensors/ahi

```
In [1]: urls2dwn = ['https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/
         https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS H09 2024
         https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS_H09_2024
         'https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS H09 2024
         https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS_H09_2024
         https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS_H09_2024
         https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS_H09_2024
         https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS H09 2024
         https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS_H09_2024
         https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS_H09_2024
         https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS_H09_2024
         https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS_H09_2024
         https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS_H09_2024
         https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS H09 2024
         https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS_H09_2024
         https://noaa-himawari9.s3.amazonaws.com/AHI-L1b-Japan/2024/03/02/1600/HS_H09_2024
```

```
import requests
import os

# Specify the local directory where you want to save the files.
# Local_directory = input("Enter the path to the download folder: ")
local_directory = "Output_data"
# Ensure that the local directory exists; create it if it doesn't.
os.makedirs(local_directory, exist_ok=True)
```

```
# Iterate through the URLs and download files.
 for urld in urls2dwn:
     # Extract the filename from the URL.
     ntw = urld.split('/')[-1]
     # Construct the complete path to save the file in the local directory.
     file_path = os.path.join(local_directory, ntw)
     # Send an HTTP GET request to the URL.
     resp = requests.get(urld)
     # Check if the response is successful (status code 200).
     if resp.status_code == 200:
         # Write the content to the file in binary mode.
         with open(file_path, "wb") as file:
             file.write(resp.content)
         print(f"File '{ntw}' downloaded and saved to '{local_directory}'.")
         print(f"Failed to download '{ntw}' from the URL: {urld}")
File 'HS H09_20240302_1600_B01_JP01_R10_S0101.DAT.bz2' downloaded and saved to 'Outp
File 'HS_H09_20240302_1600_B02_JP01_R10_S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
File 'HS_H09_20240302_1600_B03_JP01_R05_S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
File 'HS H09 20240302 1600 B04 JP01 R10 S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
File 'HS H09_20240302_1600_B05_JP01_R20_S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
File 'HS_H09_20240302_1600_B06_JP01_R20_S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
File 'HS_H09_20240302_1600_B07_JP01_R20_S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
File 'HS_H09_20240302_1600_B08_JP01_R20_S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
File 'HS_H09_20240302_1600_B09_JP01_R20_S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
File 'HS H09 20240302 1600 B10 JP01 R20 S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
File 'HS_H09_20240302_1600_B11_JP01_R20_S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
File 'HS_H09_20240302_1600_B12_JP01_R20_S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
File 'HS_H09_20240302_1600_B13_JP01_R20_S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
File 'HS_H09_20240302_1600_B14_JP01_R20_S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
File 'HS_H09_20240302_1600_B15_JP01_R20_S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
File 'HS H09 20240302 1600 B16 JP01 R20 S0101.DAT.bz2' downloaded and saved to 'Outp
ut data'.
```

Loading and Visualizing Satellite Data

SatPy is well-suited for working with geostationary satellite data, such as GOES-R or MSG:

```
In [4]: # Importing the warnings module and setting it to ignore all warnings.
# This is useful to prevent unnecessary warning messages from cluttering the notebo
import warnings
warnings.filterwarnings('ignore')
In [5]: from satpy.scene import Scene
# Importing Scene from the satpy module. Scene is used to represent satellite data
# and allows for operations like reading, resampling, compositing, and saving data.

from satpy import find_files_and_readers
# Importing find_files_and_readers from satpy. This function is used to automatical
# Locate satellite data files and determine the appropriate reader based on the
```

This line imports the debug_on function from the satpy.utils module, which is used to enable detailed debug logging in Satpy. This can be helpful for troubleshooting and understanding the internal workings of Satpy processes.

In [6]: from satpy.utils import debug_on

metadata and contents of the files.

Searching for Native MSG Data

```
Out[9]: {'ahi_hsd': ['Output_data\\HS_H09_20240302_1600_B01_JP01 R10 S0101.DAT.bz2',
            'Output_data\\HS_H09_20240302_1600_B02_JP01_R10_S0101.DAT.bz2',
            'Output data\\HS H09 20240302 1600 B03 JP01 R05 S0101.DAT.bz2',
            'Output_data\\HS_H09_20240302_1600_B04_JP01_R10_S0101.DAT.bz2',
            'Output_data\\HS_H09_20240302_1600_B05_JP01_R20_S0101.DAT.bz2',
            'Output_data\\HS_H09_20240302_1600_B06_JP01_R20_S0101.DAT.bz2',
            'Output data\\HS H09 20240302 1600 B07 JP01 R20 S0101.DAT.bz2',
            'Output_data\\HS_H09_20240302_1600_B08_JP01_R20_S0101.DAT.bz2',
            'Output_data\\HS_H09_20240302_1600_B09_JP01_R20_S0101.DAT.bz2',
            'Output_data\\HS_H09_20240302_1600_B10_JP01_R20_S0101.DAT.bz2',
            'Output_data\\HS_H09_20240302_1600_B11_JP01_R20_S0101.DAT.bz2',
            'Output_data\\HS_H09_20240302_1600_B12_JP01_R20_S0101.DAT.bz2',
            'Output data\\HS H09 20240302 1600 B13 JP01 R20 S0101.DAT.bz2',
            'Output_data\\HS_H09_20240302_1600_B14_JP01_R20_S0101.DAT.bz2',
            'Output_data\\HS_H09_20240302_1600_B15_JP01_R20_S0101.DAT.bz2',
            'Output data\\HS H09 20240302 1600 B16 JP01 R20 S0101.DAT.bz2']}
In [10]:
        from glob import glob # Import the glob module to find files using pattern matchin
In [11]: fnames = glob('Output_data/*.bz2')
         # List all files matching the specified pattern in the directory, useful for handli
         # scn = Scene(reader = 'seviri_l1b_native', filenames = fnames) # Create a Scene o
In [12]: fnames = glob('/home/jhbravo/input/AHI/*.bz2')
         # The above line uses the glob module to find all files in the specified directory
         # that match the given pattern (i.e., all files with a .nat extension from a specif
```

SatPy always expects the original file names!

So, do not change them when saving the data on your local machine. Otherwise, SatPy will not be able to open the files.

```
In [13]: # Creating a Scene object using the file information gathered by find_files_and_rea
scn = Scene(fMSGn)

In [14]: # Accessing the attributes of the Scene object to retrieve metadata and other infor
scn.attrs

Out[14]: {}

In [15]: # Creating a Scene object from the filenames specified in fMSGn
scn = Scene(filenames = fMSGn)

In [16]: # Accessing the attributes of the Scene object to view metadata information
scn_attrs = scn.attrs

In [17]: # Retrieve and print all available dataset names in the scene
dataset_names = scn.all_dataset_names()
print(dataset_names)
```

```
['B01', 'B02', 'B03', 'B04', 'B05', 'B06', 'B07', 'B08', 'B09', 'B10', 'B11', 'B12', 'B13', 'B14', 'B15', 'B16']
```

The scn.load(['IR_108'], upper_right_corner='NE') line in ther code bellow is used for loading a specific dataset from a satellite scene in Satpy. Let's break down what each part does:

- 1. scn: This is your Satpy Scene object, which contains data from satellite files that you've previously loaded.
- 2. .load(): This method is used to load specific datasets from the satellite files into memory, making them ready for processing and analysis.
- 3. ['IR_108']: This is a list containing the names of the datasets you want to load. In this case, you're loading the dataset named IR_108, which typically refers to infrared imagery at a wavelength of 10.8 micrometers. This wavelength is often used for cloud imaging, among other applications.
- 4. upper_right_corner='NE': This parameter specifies how the data should be oriented when loaded. NE means that the upper right corner of the data should be in the northeast. This can be important for getting the geographical orientation correct, especially when dealing with global or hemispherical datasets.

After running this line, the IR_108 dataset will be loaded into your scene and ready for further processing, such as visualization or analysis.

```
In [18]: scn.load(['B13'], upper_right_corner='NE')
```


The scn.keys() method in Satpy is used to retrieve a list of all the dataset keys available in the currently loaded Scene object.

```
In [19]: scn.keys()
```

Out[19]: [DataID(name='B13', wavelength=WavelengthRange(min=10.2, central=10.4, max=10.6, u nit='\mum'), resolution=2000, calibration=<calibration.brightness_temperature>, modifiers=())]

```
In [20]: # Show the 'IR_108' dataset using Satpy's built-in visualization capabilities
    scn.show('B13')
```


Out[20]:



```
In [21]: %matplotlib inline
    # Plot the 'IR_108' channel using matplotlib's imshow function
    scn['B13'].plot.imshow()
```

Out[21]: <matplotlib.image.AxesImage at 0x227155e6890>





In [22]: # Import the matplotlib library for creating visualizations in Python
import matplotlib.pyplot as plt


```
In [23]: # Create a figure and an axes object with specified figure size
    fig, ax = plt.subplots(figsize=(10,10))

# Display the data from the 'IR_108' channel of the satellite scene using a graysca
    plt.imshow(scn['B13'].values, cmap="Greys")

# Hide the axis labels and ticks to focus on the image only
    ax.set_axis_off()


# Add a colorbar to the plot with a fraction size of the plot, useful for scale/ref
    plt.colorbar(fraction=.04)

# Display the figure with all its components
    plt.show()
```



In [24]: # Accessing the 'IR_108' dataset from the Scene object 'scn'
- 'scn' is a Scene object, used for handling satellite data.
- 'IR_108' specifies an infrared channel at 10.8 micrometers.
This dataset is used for cloud imaging, surface temperature, and atmospheric anal scn['B13']

Out[24]: xarray.DataArray 'clip-81aebbc686e47a4f4273921d6236193b' (**y**: 1200, **x**: 1500)



▼ Coordinates:

crs	() object PROJCRS["unknown",BASEGEOGCRS["u	
у	(y) float64 4.599e+06 4.597e+06 2.201e+06	
x	(x) float64 -2.149e+06 -2.147e+06 8.49e+05	

► Indexes: (2)

► Attributes: (18)

Radiance Calibration

```
In [25]: # Load the data for the 10.8µm band.

# The parameter [10.8] specifies the wavelength of the band in micrometers.

scn.load([10.3],

# Specify the calibration to radiance values.

# "radiance" calibration converts the data to radiometric units (mW m-2 sr

calibration=["radiance"],

# Set the orientation of the image.

# "upper_right_corner='NE'" aligns the image with its upper right corner t

upper_right_corner='NE')
```

Brightness Temperature Calibration

```
In [26]: # Load the data for the 10.8µm band again, this time for a different calibration.
scn.load([10.3],

# Specify the calibration to brightness temperatures.
# "brightness_temperature" calibration converts the data to temperature un calibration=["brightness_temperature"],

# Maintain the same orientation as before.
upper_right_corner='NE')
```

```
In [27]: # List all the datasets currently loaded into the Scene object 'scn'
available_datasets = scn.keys()
print(available_datasets)
```

[DataID(name='B13', wavelength=WavelengthRange(min=10.2, central=10.4, max=10.6, unit=' μ m'), resolution=2000, calibration=<calibration.brightness_temperature>, modifier s=()), DataID(name='B13', wavelength=WavelengthRange(min=10.2, central=10.4, max=10.6, unit=' μ m'), resolution=2000, calibration=<calibration.radiance>, modifiers=())]

```
In [28]: # Convert the keys view to a list to enable indexing
    keys_list = list(scn.keys())

# Access the second dataset key
    second_dataset_key = keys_list[1]

# Extract the central wavelength from the 'wavelength' attribute of the second data
    central_wavelength = second_dataset_key['wavelength'][1]

# Print the central wavelength and the key for the second dataset
    print("Central Wavelength:", central_wavelength, "µm")
    print("Second Dataset Key:", second_dataset_key)
```

Central Wavelength: 10.4 μm Second Dataset Key: DataID(name='B13', wavelength=WavelengthRange(min=10.2, central= 10.4, max=10.6, unit='μm'), resolution=2000, calibration=<calibration.radiance>, mod ifiers=())

```
In [29]: # Create a figure and two subplot axes, arranged horizontally, with specified size
         fig, (ax1, ax2) = plt.subplots(1, 2, figsize=(14,6))
         # Display the values of the second dataset in the Scene on the first subplot (ax1)
         im1 = ax1.imshow(scn[scn.keys()[1]].values, cmap="Greys")
         # Remove the axis labels and ticks for ax1
         ax1.set_axis_off()
         # Display the values of the first dataset in the Scene on the second subplot (ax2)
         im2 = ax2.imshow(scn[scn.keys()[0]].values, cmap="Greys")
         # Remove the axis labels and ticks for ax2
         ax2.set_axis_off()
         # Set the title for ax2
         ax2.set_title("10.8µm Brightness temperature")
         # Set the title for ax1
         ax1.set_title("10.8μm Radiance")
         # Add a colorbar next to ax1, adjusting its size
         fig.colorbar(im1, ax=ax1, fraction=.05)
         # Add a colorbar next to ax2, adjusting its size
         fig.colorbar(im2, ax=ax2, fraction=.05)
         # Display the figure
         plt.show()
```

```
10.8µm Radiance
                                                             10.8µm Brightness temperature
                                                                                             - 280
                                                                                             - 270
                                                                                             - 260
                                                                                             - 250
                                                                                             - 240
                                                                                             230
In [31]: # Access the x-coordinates (longitude values) of the 'IR_108' data array in the Sce
          scn['B13'].x
Out[31]: xarray.DataArray 'x' (x: 1500)
         array([-2148999.961386, -2146999.961422, -2144999.961458, ..., 844999.984817,
                  846999.984781, 848999.984745])
         ▼ Coordinates:
                                   object PROJCRS["unknown",BASEGEOGCRS["u...
            crs
                               (x) float64 -2.149e+06 -2.147e+06 ... 8.49e+05
            Х
                                                                                       ► Indexes: (1)
         ▼ Attributes:
            units:
                               meter
In [32]: # define palette (matplotlib style)
          cmap = ['#ffffff', '#ffffff', '#ffffff', '#ffffff', '#b6ffb6', '#79ff79'
                  '#0028a2', '#000079', '#fbfb00', '#e7e700', '#d2d200', '#baba00', '#a6a600'
                  '#aaaaaa', '#a6a6a6', '#9e9e9e', '#969696', '#8e8e8e', '#868686', '#7d7d7d'
                  '#313131', '#282828', '#202020', '#181818', '#141414', '#000000', '#000000'
In [33]: # Retrieve the area definition (spatial reference) associated with the 'IR_108' dat
          area_def = scn['B13'].attrs['area']
In [34]: # Convert the area definition to a Cartopy Coordinate Reference System (CRS) object
          cartopy_crs = area_def.to_cartopy_crs()
In [35]: # Convert the area definition to a Cartopy CRS (Coordinate Reference System) object
          crs = area_def.to_cartopy_crs()
          # Create a figure with specific size
          fig = plt.figure(figsize=(10,10))
```

```
# Add axes to the figure with the specified projection (crs)
ax = plt.axes(projection=crs)


# Draw coastlines on the map for reference
ax.coastlines()

# Add gridlines to the map
ax.gridlines()


# Display the 'IR_108' data as an image, using the converted Cartopy CRS for correct plt.imshow(scn['B13'], transform=crs, extent=crs.bounds, origin='upper')

# Add a color bar to the plot, labeling it with the data's unit of measurement plt.colorbar(label=scn['B13'].attrs['units'])

# Display the plot plt.show()
```



```
In [36]: # Import the NumPy library, which provides support for large, multi-dimensional arr
         import numpy as np
In [37]: # Create an array of levels for the color map, spanning from -109 to 56, with the s
         levels = np.linspace(-109, 56, num=len(cmap))
         # Create a BoundaryNorm object for the color map to ensure proper coloring based on
         norm = plt.cm.colors.BoundaryNorm(levels, len(levels))
         # Create a ListedColormap using the 'cmap' colors and the custom norm
         irmap = plt.cm.colors.ListedColormap(cmap)
         # Display results
         # Convert the area definition to a Cartopy CRS (Coordinate Reference System) object
         crs = area_def.to_cartopy_crs()
         # Create a figure with specific size
         fig = plt.figure(figsize=(10,10))
         # Add axes to the figure with the specified projection (crs)
         ax = plt.axes(projection=crs)
         # Draw coastlines on the map for reference
         ax.coastlines()
         # Add gridlines to the map
         ax.gridlines()
         # Display the 'IR_108' data as an image, using the converted Cartopy CRS for correc
         # Set the minimum and maximum values for the color map (vmin and vmax)
         # Use the custom 'irmap' color map and apply the 'norm' for color scaling
         plt.imshow(scn['B13'], transform=crs, extent=crs.bounds, origin='upper', vmin=-109
         # Add a color bar to the plot, labeling it with the data's unit of measurement
         plt.colorbar(label=scn['B13'].attrs['units'])
         # Display the plot
         plt.show()
```



In []: